How To Upgrade SOLIDWORKS Electrical Standalone

TITLE:	How To Upgrade SOLIDWORKS Electrical Standalone
DATE:	September 2026
SUBJECT:	SOLIDWORKS Electrical Standalone Upgrade
ABSTRACT:	This guide gives instructions for upgrading SOLIDWORKS Electrical. It is written for standalone installations of SOLIDWORKS Electrical



This guide gives instructions for upgrading SOLIDWORKS Electrical. It is written for standalone installations of SOLIDWORKS Electrical. In this configuration, all program components are on the same computer. If your software is installed in a client-server configuration (a server computer hosts the program data, collaborative server, and SQL server, while each client computer hosts the user application), please refer to the SOLIDWORKS Electrical Client-Server Upgrade Guide (available in our Help Center). Please contact Hawk Ridge Systems Technical Support if you are unsure of your SOLIDWORKS Electrical configuration type.

SOLIDWORKS Electrical uses the same installation manager as other SOLIDWORKS products, including the 3D CAD software. If upgrading other SOLIDWORKS products along with Electrical, please also refer to their upgrade guides for further instructions.

This is not a troubleshooting guide. Please visit our Help Center or contact Hawk Ridge Systems Technical Support if you have any technical issues with SOLIDWORKS Electrical.

This document is only to be distributed to and used by Hawk Ridge Systems customers. Any other use is prohibited.

©2026 Hawk Ridge Systems

Contents

How To Upgrade SOLIDWORKS Electrical Standalone 2025 1
Before Upgrading 2
Licensing 3
Configuration Requirements 3
Standalone Upgrade 4
Appendix: License Deactivation ..... **Error! Bookmark not defined.**
Online Deactivation ..... **Error! Bookmark not defined.**
E-mail Deactivation ..... **Error! Bookmark not defined.**

Before Upgrading

Hawk Ridge Systems highly recommends taking a moment before installing SOLIDWORKS Electrical and checking that you are ready to load your new software. First, ensure that your computer meets minimum system requirements and that your video card passes certification checks. Also, confirm that the hard drive has enough space to have at least 15% free space after the full installation. Back-up data such as any shared Toolbox library, Design Library, Template files, or a data management vault. As always, verify workmates, customers, or vendors are all on the same version of SOLIDWORKS Electrical. Older versions of SOLIDWORKS Electrical cannot open files from newer versions.

1. Confirm your community's working version.

    - Ensure that colleagues, customers, and vendors with whom you share files are all on the same version to which you are upgrading.
    - You can only have one version of SOLIDWORKS Electrical installed on a single computer, so any previous versions will be uninstalled.
    - In the client-server configuration, all installations must be running the same major year version of SOLIDWORKS Electrical. A future version server installation will not be accessible to a client installation of an earlier version.

2. Back-up your data.

    - It is strongly recommended that you **archive your environment** prior to performing any upgrade or maintenance of SOLIDWORKS Electrical. This will save a copy of all your program data (projects, components, symbols, etc.) into one compressed file. To do this, click the **Archive Environment** button within the SOLIDWORKS Electrical application and run through the wizard. Note that the archive may take several hours to create, so we recommend running this process overnight.



- If you have related SOLIDWORKS files, it is recommended you make backup copies of these too. Any templates or design libraries should also be saved to a backup folder.

3. Obtain your SOLIDWORKS installation media.

- The latest version of the SOLIDWORKS Installation Manager can be downloaded from the SOLIDWORKS downloads page.
- The Installation Manager can be used to download the necessary files and complete the upgrade in one process.
- The Installation Manager can also be used to download the full SOLIDWORKS installation files ahead of the upgrade. This complete file set is approximately 21 GB and is equivalent to the DVDs. This is useful if SOLIDWORKS Electrical is being upgraded on several computers, as the files can be downloaded once then copied to those computers via the network or a removable storage device.
- You can also use the SOLIDWORKS DVDs, if available.

Licensing

SOLIDWORKS Electrical can be used with standalone and network licenses. Note that the license type differs from the installation configuration, which can be standalone or client-server (this guide is for the standalone configuration). Either license type can be used with either configuration.

If you have a standalone license, you will need to activate SOLIDWORKS Electrical after upgrading. You will be automatically prompted to do this when launching the application after an upgrade. If you are upgrading SOLIDWORKS at the same time as SOLIDWORKS Electrical, you will need to launch SOLIDWORKS to complete the activation. Refer to our guide titled Product Activation for more information on activation methods. You may also deactivate a standalone license on a particular computer by following the steps in the Appendix. This will allow the license to be activated on another computer.

If you have a network license, the SolidNetWork License Manager on the license server computer needs to be of a version at or above the version of SOLIDWORKS Electrical to which you are upgrading. If this is not already the case, refer to our Network Server Installation guide to install and activate a suitable version of the SolidNetWork License Manager.

Configuration Requirements

SOLIDWORKS Electrical includes Microsoft SQL Server 2022 Express in the installation for new installations but will not automatically upgrade SQL.

If you are upgrading SOLIDWORKS Electrical 3D, you must either upgrade SOLIDWORKS along with Electrical 3D or have already upgraded SOLIDWORKS on your computer. SOLIDWORKS, SOLIDWORKS Electrical Schematic and SOLIWORDS Electrical 3D must all be of the same version and service pack.

Standalone Upgrade

REMINDER: If upgrading from a previous version of SOLIDWORKS Electrical, we strongly recommend archiving your environment proceeding.


SQL Server Upgrade:

If you are upgrading from a previous version of Solidworks Electrical, you may need to upgrade your SQL Server Express to 2022 or newer since **SQL 2019 and older is no longer compatible**. If your SQL Server Express is already running 2022 or newer you can ignore this.


For information about how to the upgrade SQL please see the full Microsoft article here: https://docs.microsoft.com/en-us/sql/database-engine/install-windows/upgrade-sql-server?view=sql-server-ver15

Solidworks Electrical Upgrade:

1. Log into the computer as an administrator.
2. Disable all anti-virus and anti-spyware tools and turn off Windows User Account Control.
3. Locate your SOLIDWORKS installation media (download or DVD) and launch the setup application (setup.exe). You should see the Welcome screen for the SOLIDWORKS Installation Manager. Select **Install on this computer** then click **Next**.




4. You will then see the Serial Number screen. This should already contain your existing SOLIDWORKS licenses. Note that you do not need to enter multiple serial numbers if your SOLIDWORKS serial number is the same as your SOLIDWORKS Electrical serial number. If you are only upgrading the SOLIDWORKS Electrical Schematic application, the serial number should be entered in the corresponding field. Only check and enter the SOLIDWORKS Electrical 3D option if you have a separate license serial number for it. Click **Next**.




5. The Installation Manager will verify your serial number and perform an automatic system check for any existing versions of SOLIDWORKS or SOLIDWORKS Electrical. Take note of any messages or warnings during this step then click **Next**.

6. If upgrading from one major version to another (e.g. 2025 to 2025), the Installation Options screen may give you the option to create a new installation. Because multiple versions of SOLIDWORKS Electrical cannot be installed on the same computer, select **Upgrade SOLIDWORKS**.




7. At the Summary screen, you can change the settings and options defined for the upgrade. To do so, click **Change** on the right side of each option.



8. Click **Change** next to Products to go to the Product Selection screen. Scroll down and ensure that SOLIDWORKS Electrical is checked on. Nested here are the individual Electrical components. Check these against the information below. Click **Back to Summary** when finished.


- **SOLIDWORKS Electrical Schematic** is the 2D electrical schematic design application and should be checked on.
- **SOLIDWORKS Electrical 3D** is the add-in for the main SOLIDWORKS application. It may not be available if your license does not include it, but if it does, ensure that you are installing SOLIDWORKS as well. They must be of the same version and service pack.
- **Collaborative Server** is used to communicate between the application and the SQL server. This option should be checked on for a standalone upgrade.
- **Data** includes the SQL server and program data used for the application (projects, symbols, manufacturer parts, templates, etc.). This option should be checked on for a standalone upgrade.



9. At the Summary screen, click **Change** next to Electrical Options. Check the following options and click **Back to Summary** when finished.


- **Data Location** specifies the directory containing all program data. The default is C:\ProgramData\SOLIDWORKS Electrical. This should be the same as the existing directory used for your program data. If it is not already, click **Browse** to point this to the correct location.
- **Collaborative Server** specifies the machine name and port number of the collaborative server. The defaults are localhost and 26666, respectively. These settings should correspond to those for your existing installation.
- **SQL Server** specifies the name of the SQL server (the default is localhost\TEW_SQLEXPRESS) that hosts the Electrical databases and the password that is used to connect to it. Check that the SQL server name correctly matches the existing SQL server on your computer. If it is incorrect, click **Browse** to find and select the correct SQL server then make sure that **Use an existing SQL Server database** is selected.
- For an upgrade, we recommend changing the authentication type to **Connect using SQL Server Authentication** to prevent any permissions issues from affecting the upgrade. Make the login **sa** and use the appropriate password. T This will be **SolidworksElectricalSQLpwd4ew** (or **SQLpwd4ew** if your first time install of the software was version 2022 or older), unless explicitly changed by the administrator during the original installation.

Note: SQL Server 2019 or newer is required for the upgrade. If not previously installed select "Install new instance of SQL server" to proceed with the upgrade.




10. Confirm that all the information on the Summary screen is correct. Accept the license agreement then click **Install Now** to begin the upgrade.

11. When the upgrade is complete, you will be asked to join the SOLIDWORKS Customer Experience Improvement Program. We recommend joining this, as it provides software performance information to SOLIDWORKS. The information this sends to SOLIDWORKS is treated confidentially and does not result in the transfer of any file information. After making the selection, click the **Finish** button to complete the upgrade.



12. When the software is launched for the first time after the upgrade, you may need to activate the license (if using standalone licensing). Follow the prompts to complete this. You will also be prompted to accept the license agreement.

13. Finally, you will be prompted to update the program data for this version of SOLIDWORKS Electrical. Proceed through this wizard to complete the installation and begin using the software.



For additional support, existing customers can submit a ticket or new customers can contact Hawk Ridge Systems.