

How To Plan For A SOLIDWORKS 2022 Upgrade

35 50	LIDWORKS Premium	Cancel V
ABSTRACT:	Comprehensive guide on planning an upgrade for S	OLIDWORKS 2022
SUBJECT:	SOLIDWORKS Upgrade	
DATE:	September 2021	
TITLE:	How To Plan For A SOLIDWORKS 2022 Upgrade	



Introduction

This document is meant to give a general overview of the installation process and provide a simple checklist for system administrators getting ready to deploy SOLIDWORKS and PDM software. Detailed information for installation is available through the Hawk Ridge support portal here: <u>Help Desk Support</u> <u>Portal</u>

When implementing any new version, compatibility is a significant concern. Network-based licensing requires that the license server is updated first to the new version. Without an updated license server, clients will be unable to check out the new version license. In PDM Standard and Professional PDM environments, clients must have the <u>same major version</u> as their target vault server.

©2021 Hawk Ridge Systems

USA: 1.877.266.4469



Contents

Introduction	1
SOLIDWORKS Standalone Installation	2
SOLIDWORKS Network Licensed Setup	5
PDM Professional Installation	

SOLIDWORKS Standalone Installation

SOLIDWORKS standalone licensing is activation-based meaning for each stand-alone license one user can activate on one machine at a time.

- Client Products (e.g. SOLIDWORKS) × × Windows 11, 64-bit (SW2022 SP2) \checkmark Windows 10, 64-bit Windows 7 SP1, 64-bit × X **MS Office** 2016, 2019, Microsoft Excel and Word 2013, 2016, 2019 2016, 2019 2021 (SW2022 SP2) SOLIDWORKS 2020 SOLIDWORKS 2021 SOLIDWORKS 2022 Hardware Processor 3.3 GHz or higher 16 GB or more RAM PDM Contributor/Viewer or Electrical Schematic: 8 GB or more Graphics Certified cards and drivers Drives SSD drives recommended for optimal performance Hypervisors (Virtual Environments) 7.0 U3c VMware vSphere ESXi 6.7 6.7 U3 VMware Workstation 16.2.3 15.5 15 2019 Microsoft Hyper-V 2019 2019 17.1.2 Parallels Desktop, Mac 14 16.0 Citrix XenServer 7.6 8.2 8.2 CU1
- Compatibility



For more information on hardware recommendations for SOLIDWORKS, see our guides here:

2022 Recommended Hardware

2022 Comprehensive Hardware Guide

SOLIDWORKS requires a video card with a certified driver. It's best to update your video driver to the certified version found here before installation:

• Licensing

Each stand-alone license is only allowed 1 active machine per standalone license. If you are planning to upgrade one computer from a previous version, the activation will carry over. However, if you need to switch machines or install on a new machine, you will first need to transfer the license from your old machine.

To transfer your license: open SOLIDWORKS then use the Help > Deactivate Licenses feature. This feature deactivates the product on your current machine so it can be reactivated on the new machine. You then go to the new computer, install SOLIDWORKS then start it and select Help > Activate Licenses to proceed with the activation process.

Depending on your activation status, you may also need to change the serial number of the installed version of SOLIDWORKS. For example, if you purchased a new license of SOLIDWORKS Premium and wanted to switch from a SOLIDWORKS Standard license.



To change the serial number of your SOLIDWORKS license: go to the windows control panel and select 'Programs and Features.' Find SOLIDWORKS in the list of programs highlight it and select **Change**:

0	Programs and Features						_		×
~	→ * ↑ 🖸 « Programs	√ Ö	Search Program	ns and	Features	P			
	Control Panel Home	Uninsta	II or chan	ge a program					
•	View installed updates Turn Windows features on or	To uninstall a program, select it from the list and then click Uninstall, Change, or Repair.							
	off	Organize 🔻	Uninstall	Change					?
		Name		^		Publisher			^
		SOLIDWOR	KS 2021			SolidWorks Co	rporatio	DN	
		٤				_			» ×
		SW	SolidWorks	Corporation Proc	duct version: Help link:	29.0.0.2051 http://www.sol	idwork	s.com	

This will launch the SOLIDWORKS installation manager. Select the option to 'modify' your current installation then input your new serial number. REMEMBER, if you currently have SOLIDWORKS active on your machine, you will need to deactivate this license first.

Access

SOLIDWORKS installation requires the use of an unrestricted administrator account. Turning off "Windows user account controls" (UAC), and any anti-virus software is also recommended during installation.

• Copy Settings Wizard

The copy settings Wizard can be used to copy all the configuration of one version of SOLIDWORKS to the next. Making it possible to backup and restore SOLIDWORKS configuration across the version.

Upgrading Hole Wizard/Toolbox
 The Hole Wizard/toolbox is a critical component of SOLIDWORKS. To avoid data loss, be sure to back up your Toolbox folder – usually found at C:\SOLIDWORKS Data. For more information, please see our comprehensive toolbox guide here: <u>Comprehensive Toolbox Guide</u>



SOLIDWORKS Network Licensed Setup

The first step in a SOLIDWORKS upgrade is to upgrade the license server. License servers are backward compatible but not forwards compatible. Therefore, if you plan to use SOLIDWORKS 2022, you must have an updated 2022 license server. A detailed guide to the 2022 license manager installation can be found here:

2022 Network Server License Manager Installation Guide

 Network server version Before starting the upgrade process, review the operating system compatibility here:

Server Products (e.g. SOLIDWORKS PDM)					
Windows Server 2022	×	×	(SW2022 SP4)		
Windows Server 2019	~	~	~		
Windows Server 2016	~	~	~		

- Support for virtual machines
 Currently only the following virtual machine platforms will allow activation of a license server:
 VMWare, Microsoft Hyper-V, Parallels, and Citrix Xen.
- <u>Client Installation</u>

SOLIDWORKS network client installation is the same as a stand-alone installation. The network license key is used to install SOLIDWORKS, and no activation is required. All clients must be able to freely communicate with the license server on port 25734 and 25735.

- Migration from standalone
 - i When switching workstations to use a network license, the first step will be to designate and install the SNL (SolidNetwork License) manager on the new license server.
 - ii To remove the previous activations. Client installations will need to be modified to use the network serial number and receive their licenses from the license server. Follow the procedure to switch the licenses using the windows control panel -> Programs and Features -> highlight SOLIDWORKS and select 'change.' This will give the option to change the installed serial number and add the client's license manager.

• Admin image deployment

Creating an admin image for deployment provides a method to create a single image to be pushed out to each client machine. Images can be customized per machine to change installation modules for specific workstations.

PDM Version

Before updating your clients and license server, it is essential to consider if you have an active PDM system as this system will need to be upgraded as well. With SOLIDWORKS Professional, Standard or Workgroup PDM clients, if you wish to use a newer version of SOLIDWORKS your PDM vault and client software will need to be upgraded as well. A newer client will be unable to connect to an older vault.



License Troubleshooting

The most common error associated with a network license is the Windows firewall blocking access to the license server. Make sure that the ports 25734 and 25735 are open on all clients and inbound on the license server.

PDM Professional Installation

PDM Professional consists of three modules: Archive server, Database server, and clients. Each of these must be updated to work together. **Before upgrading, be sure to have a backup of your SQL database and vault data.** Once you have current backups, to complete the installation, you will need to have logins to the SQL SA user account and Vault Admin account.

• Change in licensing method

2015 added activation-based licensing for PDM using the SolidNetwork license manager. Licenses for PDM are now managed through the SNL with FlexLM, giving administrators real-time information on license usage.

- SQL Server installation
- PDM does not include a copy of the SQL Server. Either a current installation will need to be used or a new install created. Hawk Ridge Systems can provide installation media for SQL server 2014. PDM Professional 2022 is only compatible with SQL Server 2016 and newer.
- Vault and Client Version All clients must be running the same year version of the PDM software as the vault.

Client Compatibility – CAD Editor

	SOLIDWORKS 2020 (EDU 2020-2021)	SOLIDWORKS 2021 (EDU 2021-2022)	SOLIDWORKS 2022 (EDU 2022-2023)
Client Products (e.g. SOLIDWORKS)			
Windows 11, 64-bit	×	×	(SW2022 SP2)
Windows 10, 64-bit	~	~	~
Windows 7 SP1, 64-bit	~	×	×



	SOLIDWORKS 2020	SOLIDWORKS 2021	SOLIDWORKS 2022		
Hardware					
Processor		3.3 GHz or higher			
RAM	16 GB or more PDM Contributor/Viewer or Electrical Schematic: 8 GB or more				
Graphics	Certified cards and drivers				
Drives	SSD drives recommended for optimal performance				
Hypervisors (Virtual Environments)					
VMware vSphere ESXi	6.7	6.7 U3	7.0 U3c		
VMware Workstation	15	15.5	16.2.3		
Microsoft Hyper-V	2019	2019	2019		
Parallels Desktop, Mac	14	16.0	17.1.2		
Citrix XenServer	7.6	8.2	8.2 CU1		

Archive Server Compatibility

Server Products (e.g. SOLIDWORKS PDM))		
Windows Server 2022	×	×	(SW2022 SP4)
Windows Server 2019	~	×	~
Windows Server 2016	×	×	~
	SOLIDWORKS 2020	SOLIDWORKS 2021	SOLIDWORKS 2022

	(EDU 2020-2021)	(EDU 2021-2022)	(EDU 2022-2023)
MS SQL			
SQL 2019	~	SQL 2019 CU4 required	SQL 2019 CU4 required
SQL 2017	~	~	~
SQL 2016	~	~	~
SQL 2014	SQL 2014 SP3 required	SQL 2014 SP3 required	×



Database and Archive Server Compatibility

Products	Start of Support	End of Support ¹
Windows 11, 64-bit	SW 2022 SP2	Active
Windows 10, 64-bit	SW 2015 SP5	Active
Windows Server 2022	SW 2022 SP4	SW 2028 SP5
Windows Server 2019	SW 2019 SP3	SW 2025 SP5
Windows Server 2016	SW 2017 SP2	SW 2023 SP5
SQL Server 2019	SW 2020 SP0	SW 2026 SP5
SQL Server 2017	SW 2018 SP0	SW 2024 SP5
SQL Server 2016	SW 2017 SP0	SW 2023 SP5
SQL Server 2014	SW 2015 SP0	SW 2021 SP5
Excel, Word 2021 (64-bit recommended)	SW 2022 SP2	Active
Excel, Word 2019 (64-bit recommended)	SW 2019 SP2	SW 2023 SP5
Excel, Word 2016 (64-bit recommended)	SW 2016 SP3	SW 2023 SP5
macOS Ventura (13.0)	eDrawings 2023	eDrawings 2025
macOS Monterey (12.0)	eDrawings 2022	eDrawings 2024
macOS Big Sur (11.0)	eDrawings 2021	eDrawings 2023
macOS Catalina (10.15)	eDrawings 2020	eDrawings 2022
macOS Mojave (10.14)	eDrawings 2019	eDrawings 2021