

CAMWorks Registry Reset

TITLE:	CAMWorks Registry Reset
DATE:	October 2018
SUBJECT:	Troubleshooting
ABSTRACT:	Guide on resetting your settings back to default



If you are having problems in CAMWorks with customization not working correctly or other unexplained issues, your user setting may have become corrupt. Here are the instructions on resetting the registry of the current user for CAMWorks. This will start CAMWorks with all default settings to rule out settings or registry corruption issues.


One thing you need to understand first is that we are going into registry editor, so you should be extremely careful not to modify anything except what is listed below. If you do not feel comfortable performing the steps listed below, please <u>contact us</u> for assistance.

DO NOT DELETE ANYTHING IN YOUR REGISTRY UNLESS EXPLICITLY INSTRUCTED TO.

Prior to proceeding, it is recommended you use the "CAMWorks Copy Settings" (under Start > Programs > CAMWorks > CAMWorks Copy Settings) to save a copy of your CAMWorks settings. In the following steps we will also make a hard copy straight from the registry as well.

Here are the steps:

- 1.) Close all applications including CAMWORKS and SolidWorks
- 2.) Click the START menu and search for REGEDIT, then click Enter





3.) Browse to the folder named HKEY_CURRENT_USER>Software>TekSoft

🎬 Registry Editor							
File Edit	View Favorites Help						
Computer\HKEY_CURRENT_USER\Software\TekSoft							
>	Sysinternals	^	Name				
×	TekSoft		(Default)				
	> CAMWorks		~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~				
	> CAMWorksOEM						
	CAMWorksSE	~					

4.) Right click on the folder and click EXPORT

	Regis	stry	Edit	or						
File	Edi	t	Viev	v Favo	orites	Help				
Com	Computer\HKEY_CURRENT_USER\Software\TekSoft									
		>	<u> </u>	SyncEng	jines		^		Name	
		>_	5	Sysinter	nals				ab (Default)	
		Y	٦ 🔒	[ekSoft		C II				
			>	CAM		Collapse				
			>	CAM		New				>
			>	CAM		Find				
				Secu						
		-	- testapp			Delete				
		>	۱ ا	/ero UK		Rename				
		÷	۱ N	NebEx						
		ż	<u>ا</u> ۱	Now64		Export				
	>		System		Permissions					
			Uninstall Copy Key Name			me				
	>		Vola	tile Env			-			
> HKEY_LOCAL				Go to HKEY_LOCAL_MACHINE						

5.) Name it user.reg and store it anywhere you want. We have now made a backup of our current registry

	File name:	User.reg	~	Save	
	Save as type:	Registration Files (*.reg)	~	Cancel	
Export range					
Selected branch					
HKEY_CURRENT_USER\Software\TekSoft					



6.) Right click on the TekSofts folder in HKEY_CURRENT_USER>Software>TekSofts folder and choose "Rename", append -OLD to change the entry to TekSofts-OLD.

Registry Editor							
File Edit	View	Favorites	Help				
Computer\HKEY_CURRENT_USER\Software\TekSoft-old							
>	sinternals		^	Name			
>	> 🔤 TekSoft-old				ab (Default)		
	tes	tapp			~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~		

7.) Launch CAMWorks, and try to reproduce the error. (DO NOT re-import any settings prior to testing the issue)

8.) If the issue was not resolved and you want your old settings back, you can double click the .reg file to reset your original customization.



If you have any questions regarding the information above or are unable to troubleshoot this issue, please contact Hawk Ridge Systems Technical Support at 1-877-266-4469 (US), 1-866-587-6803 (CAN), or support@hawkridgesys.com.